



## Installation of Nanoptix Ultraboard Configuration Software from disc

Insert the CD

On Windows XP or older, go to My Computer on the desktop.  
On Windows Vista, click on start, computer.

Double click your CD/DVD drive, most systems it should be D drive and it should say Nanoptix

Double click through the follow directories

Nanoptix CD V1.xx (where xx is the version number for the disc you have)  
Nanoptix Ultra Systems  
Tools  
Ultra Board Configuration Software

Double click setup (or setup.exe)

Hit OK on the welcome screen  
Click on the computer icon to start the install  
Press continue on the groups screen  
Press OK

To launch the software once installed, go to:  
Start / All Programs / Nanoptix / UltraBoard Configuration Utility

*Note:* If you're on Vista, you need to have a recent version of the configuration software, such as 1.0.19, in order to use the configuration utility. Contact Fun Company or go to [funcomfg.com/manuals](http://funcomfg.com/manuals) to download a Vista compatible version.

If you have any problems installing the Nanoptix software, contact us at 608-565-5558 or toll free 800-808-5554.